


Oracle Cluster New Node Addition is Existing Cluster



High Level Steps

- 1. Install Windows 2012 Server.
- 2. Check and Apply Pre-Requisites.
- 3. Add Node from GRID Home from Existing Node and it will copy Grid Home to New Node.
- 4. Execute Grid Config on New Node
- 5. Add Node from Oracle Database Home from Existing Node and it will copy Oracle Database Home to New Node.
- 6. Add Instance of Existing Database to New Node.

Steps for Node Addition

1.	Turn off and Disable Windows Firewall	(New Node)
2.	Add Network Adapters Public and Private	(New Node)
3.	Change Adapter Type to Bridge	(New Node)
4.	Change Name of Adapter According for Existing Nodes	(New Node)
5.	Define IP Address on Both Adapters	(New Node)
6.	Change Host Name According to Existing Nodes	(New Node)
7.	Define New Node Public Id, Private IP and VIP IP Name in Host File or DNS	(All Nodes)
8.	Ping New IP Host from All Nodes	(All Nodes)
9.	Start NFTP Service and Set Auto Start.	(New Node)
10.	Disable Windows Media Sensing (DisableDHCPMediaSense)	(New Node)



11. Connect with Database Storage.	(New Node)
12. Online ASM Disks.	(New Node)
13. Set Attribute of Read only Clear for All ASM Disk.	(New Node)
14. Adding a Node to a Grid Home	(Node 1)
15. Execute Grid Config.	(New Node)
16. Post Verify Grid	(Node 1)
17. Adding a Node to an Oracle Home	(Node 1)
18. Register New Node Virtual IP	(Node 1)
19. Create Instance on New Node of Existing Database	(Node 1)

Existing Database Nodes Configuration

Operating System: Windows 2012

Database Cluster Nodes	s = 3
Scan Name	= nodescan
192.168.18.151	Node1
192.168.18.152	node2
192.168.18.147	node3
192.168.10.151	node1priv
192.168.10.152	node2priv
192.168.10.155	node3priv
192.168.18.153	asmstorage
192.168.10.153	asmstoragepriv
192.168.18.145	node1vip
192.168.18.146	node2vip
192.168.18.148	node3vip
192.168.18.241	nodescan
192.168.18.242	nodescan
192.168.18.243	nodescan



NEW NODE Configuration

Two Network Adapters for Public and Private

Public Interface Name = Public

Private Interface Name = Private

Host Name = Node4

192.168.18.149 node4

192.168.18.150 node4vip

192.168.10.156 node3priv

Current Oracle Cluster Status

```
Administrator: Command Prompt

Microsoft Windows [Version 6.3.9600]
(c) 2013 Microsoft Corporation. All rights reserved.

C:\Users\Administrator>olsnodes -n
node1 1
node2 2
node3 3

C:\Users\Administrator>hostname
node2

C:\Users\Administrator>crsctl check crs
CRS-4638: Oracle High Availability Services is online
CRS-4537: Cluster Ready Services is online
CRS-4533: Event Manager is online
CRS-4533: Event Manager is online
CRS-4533: Event Manager is online
C:\Users\Administrator>
```




```
Administrator. Command Prompt

C:\Users\Administrator\olsnodes -n
node1
node2
node3
C:\Users\Administrator\olsnome
Node3
C:\Users\Administrator\olsnome
Node3
C:\Users\Administrator\olsnome
Node3
C:\Users\Administrator\olsnome
CRS-4538: Oracle High Availability Services is online
CRS-4539: Cluster Ready Services is online
CRS-4529: Cluster Synchronization Services is online
CRS-4533: Event Manager is online
CRS-4533: Event Manager is online
C:\Users\Administrator\_


C:\Users\Administrator\_
```




Turn off and Disable Windows Firewall (New Node)





















2. Add Network Adapters Public and Private (New Node)













3. Change Adapter Type to Bridge (New Node)










4. Change Name of Adapter According for Existing Nodes (New Node)


Public - For Public Interface

Private – For Private Interface


Interface Names should be same as Existing Nodes


























5. Define IP Address on Both Network Adapters (New Node)

Public Interface Name = Public


Private Interface Name = Private

192.168.18.149 node4


192.168.10.156 node3priv

For Public Interface
















For Private Interface


192.168.10.156 node3priv






















Verify IP Address








6. Change Host Name According to Existing Nodes (New Node)


Right Click in "This PC" or "My Computer"






Advanced System Settings > Computer Name






Advanced System Settings > Computer Name > Change







Host Name = Node4 > Click "ok"












Click "Close"



Click "Restart Now"

7. Define New Node Public Id, Private IP and VIP IP Name in Host File or DNS (All Nodes)

192.168.18.151	Node1
192.168.18.152	node2
192.168.18.147	node3
192.168.18.149	node4
192.168.10.151	node1priv



192.168.10.152	node2priv
192.168.10.155	node3priv
192.168.10.156	node4priv
192.168.18.153	asmstorage
192.168.10.153	asmstoragepriv
192.168.18.145	node1vip
192.168.18.146	node2vip
192.168.18.148	node3vip
192.168.18.150	node4vip
192.168.18.241	nodescan
192.168.18.242	nodescan
192.168.18.243	nodescan

Open command prompt "Cmd"

Notepad \\192.168.18.147\c:\windows\system32\drivers\etc\hosts

Notepad \\192.168.18.149\c:\windows\system32\drivers\etc\hosts

Notepad C:\windows\system32\driver\etc\hosts


Add Below in All Node "C:\windows\system32\driver\etc\hosts"


192.168.18.149 node4

192.168.10.156 node4priv


192.168.18.150 node4vip

















8. Ping New IP Host from All Nodes (All Nodes)

192.168.18.149 node4


192.168.10.156 node4priv

192.168.18.150 node4vip (Should not Pingable)














9. Start NFTP Service and Set Auto Start (New Node)

Open cmd


sc query W32Time

sc qc W32Time


net start W32Time

services.msc > windows time > double Click>Startup Type>Automatic>ok











Execute Services.msc






Execute Services.msc > windows Time > Double Click






Execute Services.msc > windows Time > Double Click > Startup Type > Automatic > ok






10.Disable Windows Media Sensing (DisableDHCPMediaSense) (New Node)

Open cmd Regedit







Search in Registry


HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services\Tcpip\Parameters

Add New - DWORD (32 Bit) Value


Value Name: DisableDHCPMediaSense

Value: 1


















11.Connect with Database Storage (New Node)


Iscsi initiator > click > "yes"















Target = 192.168.18.153 > Click "Quick Connect"



Target = 192.168.18.153 > Click "Quick Connect" > done







Target = 192.168.18.153 > Click "Quick Connect" > done>ok

12. Online ASM Disks (New Node)

Open command Prompt "cmd"











Diskpart




List disk






Select disk 1






Online disk






Note: don't format this disk

Select disk 2




Online disk






Note: don't format this disk > Cancel






Select disk 3




Online disk






Note: don't format this disk > Cancel





List disk






13.Set Attribute of Read only Clear for All ASM Disk (New Node)

Open command prompt "cmd"


Diskpart

List disk




diskpart






List disk






Select disk 1




Attribute disk clear readonly






Select disk 2






Attribute disk clear readonly




Select disk 3





Attribute disk clear readonly









14.Adding a Node to a Grid Home (Node 1)

Login on Node 1


Open command as administrator








Cd $\alpha \1.2.0\grid\oui\bin$







addNode.bat "CLUSTER_NEW_NODES={node4}" "CLUSTER_NEW_VIRTUAL_HOSTNAMES={node4vip}"




























It will copy CRS home to New Node








15.Execute Grid Config (New Node)

Login on Node 4 - New Node


Open command as administrator "cmd"

Cd $\alpha \$ Cd \app\11.2.0\grid\crs\config\


gridconfig.bat













Add Cluster Home in Windows Path

setx /M path "%path%;C:\app\11.2.0\grid\bin"






Re-Open Command Prompt "cmd"






Check crs status

Crsctl check crs










16.Post Verify Grid (Node 1)


Login on Node 1


Open Command Prompt "cmd"




cluvfy stage -post crsinst -n all -verbose














Till Now Node has been add in Cluster

17. Adding a Node to an Oracle Home (Node 1)


Login on Node 1

Open Command Prompt "cmd"




 $\label{lem:cdc:app} $$ Cd c:\app\oracle\product\11.2.0\dbhome_1\oui\bin $$ $$$







$addNode.bat \ "CLUSTER_NEW_NODES= \{node4\}"$






















18. Register New Node Virtual IP

(Node 1)

Note: If VIP of New not add in previous Steps then run and verify by

Verify by


Srvctl config nodeapps



Login Node 1

Open Command Prompt "cmd"





C:\Users\Administrator>srvctl add vip -n node4 -k 1 -A 192.168.18.150/255.255.255.0




19.Create Instance on New Node of Existing Database (Node 1)


Login on Node 1


Open Command Prompt "cmd"

Run "dbca"

























































Now Successfully Add New Node in Oracle Cluster







End of Document